

This is an example of inserting images and comments into a report.

Just when you thought they were not going to come... here they are! Those pretty fishes are coming to your reports.

Concepts shown

- **Comments:** You can add comments to your cells the same way you add text to them. Write a `##Dataset##Datafield` into a comment and voila, that's it. If the field is empty, no comment will be shown, otherwise the field contents will.
- **Images from database:** This is only supported on native mode. To replace an image placeholder name it as `##Dataset##DataField##Imagetype`. Where "Imagetype" is either "JPEG" or "PNG" on this version. Support for metafiles is planned, but not yet implemented. Hint: To change an image name, select it and then write its name on the names combo box at the top left on the Excel toolbar.
- **Event OnGetCellValue:** This is a generic event that allows you to modify the data before it goes to the report. In this case, we have a Paradox blob image in BMP format, and we have to convert it to a JPEG or PNG before we can send it. So, we write an OnGetCellValue event where we strip the Paradox header and convert the remaining BMP to a JPEG.